

Pioneering GTPase and Oncogene Product Development since 2010

GA13 PULL-DOWN ACTIVATION ASSAY KIT

Gα₁₃ Pull-Down Activation Assay Kit

Cat. **#** 80401

Introduction

A. Background

A structurally diverse repertoire of ligands, from photons to large peptides, activates GPCRs to elicit their physiological functions. Ligand-bound GPCRs, in turn, function as guanine nucleotide exchange factors catalyzing the exchange of GDP bound on the Ga subunit with GTP in the presence of $G\beta\gamma$, causing the dissociation of the Ga subunit from the GBy dime to form two functional units (Ga and $G\beta\gamma$). Both $G\alpha$ and $G\beta\gamma$ subunits signal to various cellular signaling pathways. Based on the sequence and functional homologies, G proteins are grouped into four families: G_{sr} , G_{ir} , GG_{ar} , and G_{12} . As increasing numbers of effectors and interacting proteins for these G proteins have been identified, the physiological processes in which G proteins participate are multiplying. Among the four subfamilies of G proteins, the function of G_{12/13} subfamily is less well understood. In this family, there are two members, G₁₂ and G₁₃, that are expressed ubiquitously. Ga12 knockout mice appeared normal. Ga13 knockout mice displayed embryonic lethality (~E9.5). The Gα13-/- mouse embryos had defective vascular systems. G₁₃ is also essential for receptor tyrosine kinase-induced migration of fibroblast and endothelial cells.

B. Assay Principle

The G α_{13} Activation Assay Kit uses configuration-specific anti-G α_{13} -GTP Mouse monoclonal antibody to measure G α_{13} -GTP levels in cell extracts or in vitro GTP γ S loading G α_{13} activation assays. Anti-G α_{13} -GTP mouse monoclonal antibody is first incubated with cell lysates containing G α_{13} -GTP. Next, the GTP-bound G α_{13} is pulled down by protein A/G agarose. Finally, the precipitated G α_{13} -GTP is detected through immunoblot analysis using anti-G α_{13} mouse monoclonal antibody.

C. Kit Components



Pioneering GTPase and Oncogene Product Development since 2010

1. Anti-G α_{13} -GTP Mouse Monoclonal Antibody (Cat. # 26902): 30 µL (1 mg/ml) in PBS, pH 7.4, containing 50% glycerol. This antibody specifically recognizes G α_{13} -GTP from all vertebrates.

2. Protein A/G Agarose (Cat. # 30301): 600 µL of 50% slurry.

3. 5X Assay/Lysis Buffer (Cat. # 30302): 30 mL of 250 mM Tris-HCl, pH 8, 750 mM NaCl, 50 mM MgCl2, 5 mM EDTA, 5% Triton X-100.

4. Anti-G α_{13} Mouse monoclonal Antibody (Cat. # 21005): 50 µL (1mg/mL) in PBS, pH 7.4, contained 50% glycerol.

5. 100X GTPyS (Cat. # 30303): 50 µl at 10 mM, use 5 µL of GTPyS for GTP-labeling of 0.5 mL of cell lysate.

6. 100X GDP (Cat. # 30304): 50 µl at 100 mM, use 5 µL of GDP for GDP-labeling of 0.5 mL of cell lysate.

7. HRP-Goat Anti-Rabbit IgG (Cat. # 29002): 50 μ L (0.4 μ g/mL) in PBS, pH 7.4, contained 50% glycerol.

D. Materials Needed but Not Supplied

- 1. Stimulated and non-stimulated cell lysates
- 2. Protease inhibitors
- 3. 4°C tube rocker or shaker
- 4. 0.5 M EDTA at pH 8.0
- 5. 1.0 M MgCl₂
- 6. 2X reducing SDS-PAGE sample buffer
- 7. Electrophoresis and immunoblotting systems

8. Immunoblotting wash buffer such as TBST (10 mM Tris-HCl, pH 7.4, 0.15 M NaCl, 0.05% Tween-20)

9. Immunoblotting blocking buffer (TBST containing 5% Non-fat Dry Milk or 3% BSA) 10. ECL Detection Reagents

E. Example Results

The following figure demonstrates example results seen with the Gα₁₃ Activation Assay Kit. For reference only.



Pioneering GTPase and Oncogene Product Development since 2010

MEF cells $\overline{- + LPA}$ kD 55 -43 -33 -26 -1 2 IP: anti-active Ga₁₃ mAb WB: anti-Ga₁₃ pAb $\overline{- - Total Ga_{13}}$ NB: anti-Ga_{13} pAb

Ga₁₃ **Activation Assay.** MEF cells were treated with (lane 2) or without (lane 1) LPA. Cell lysates were incubated with an anti-Ga₁₃-GTP monoclonal antibody (Cat. # 26902) (top panel). The precipitated active Ga₁₃ was immunoblotted with an anti-Ga₁₃ rabbit polyclonal antibody (Cat. # 21005). The bottom panel shows the Western blot with anti-Ga₁₃ of the cell lysates used (5% of that used in the top panel).

Assay Procedure

A. Reagent Preparation

IX Assay/Lysis Buffer: Mix the 5X Stock (Cat. # 30302) briefly and dilute with deionized water to make 1X buffer. Just prior to usage, add protease inhibitors such as 1 mM PMSF, 10 μg/mL leupeptin, and 10 μg/mL aprotinin.

B. Sample Preparation

Adherent Cells

1. Culture cells (one 10-cm plate, ~10⁷ cells) to approximately 80-90% confluence. Stimulate the cells with activator or inhibitor as desired.

2. Aspirate the culture media and wash twice with ice-cold PBS.

3. Completely remove the final PBS wash and add ice-cold 1X Assay/Lysis Buffer

(See Reagent Preparation) to the cells (0.5-1 mL per 10 cm tissue culture plate).

4. Place the culture plates on ice for 10-20 minutes.

5. Detach the cells from the plates by scraping with a cell scraper.

6. Transfer the lysates to appropriate size tubes and place on ice.



Pioneering GTPase and Oncogene Product Development since 2010

7. If nuclear lysis occurs, the cell lysates may become viscous and difficult to pipette. If this occurs, lysates can be passed through a 27½-gauge syringe needle 3-4 times to shear the genomic DNA.

8. Clear the lysates by centrifuging at 12,000 x g and 4°C for 10 minutes.

9. Collect the supernatant and store the sample (~1-2 mg of total protein) on ice for immediate use, or snap freeze and store at -70°C for future use.

Suspension Cells

1. Culture cells and stimulate with activator or inhibitor as desired.

2. Perform a cell count and then pellet the cells through centrifugation.

- 3. Aspirate the culture media and wash twice with ice-cold PBS.
- 4. Completely remove the final PBS wash and add ice-cold IX Assay/Lysis Buffer

(See Reagent Preparation) to the cell pellet (0.5-1 mL per 10^7 cells).

5. Lyse the cells by repeated pipetting.

6. Transfer the lysates to appropriate size tubes and place them on ice.

7. If nuclear lysis occurs, the cell lysates may become viscous and difficult to pipette. If this occurs, lysates can be passed through a 27½-gauge syringe needle 3-4 times to shear the genomic DNA.

8. Clear the lysates by centrifuging at 12,000 x g and 4°C for 10 minutes.

9. Collect the supernatant and store sample on ice for immediate use, or snap freeze and store at -70°C for future use.

C. In vitro GTP_YS/GDP Protein for Positive and Negative controls

Note: In vivo stimulation of cells will activate approximately 10% of the available $G\alpha_{_{13}}$ whereas in vitro GTP γ S protein loading will activate nearly 90% of $G\alpha_{_{13}}$.

1. Aliquot 0.5 mL of cell extract (or 1 μg of purified Gα₁₃ protein) into two microcentrifuge tubes.

2. To each tube, add 20 μ L of 0.5 M EDTA (final concentration of 20 mM).

- 3. Add 5 µL of 100 X GTPγS (Cat. # 30303) to the first tube as a positive control.
- 4. Add 5 μL of 100 X GDP (Cat. # 30304) to the second tube as a negative control.
 5. Incubate both tubes at 30°C for 30 minutes with agitation.

6. Stop loading by placing the tubes on ice and adding 32.5 μ L of 1 M MgCl₂ (final concentration of 60 mM).

D. Affinity Precipitation of Activated G Protein

1. Aliquot 0.5-1 mL of cell lysates (about 1 mg of total cellular protein) to a microcentrifuge tube.

2. Adjust the volume to 1 mL with 1X Assay/Lysis Buffer (See Reagent Preparation). 3. Add 1 μ L anti-G α_{13} -GTP antibody (Cat. # 26902).



Pioneering GTPase and Oncogene Product Development since 2010

4. Prepare the protein A/G Agarose bead slurry (Cat. # 30301) by resuspending through vertexing or titrating.

5. Quickly add 20 µL of resuspended bead slurry to above tube.

6. Incubate the tube at 4°C for 1 hour with gentle agitation.

7. Pellet the beads through centrifugation at $5,000 \times g$ for 1 min.

8. Aspirate and discard the supernatant (making sure not to disturb or remove the bead pellet).

9. Wash the beads 3 times with 0.5 mL of 1X Assay/Lysis Buffer, centrifuging and aspirating each time.

10. After the third wash, pellet the beads through centrifugation and carefully remove all the supernatant.

Resuspend the bead pellet in 20 μL of 2X reducing SDS- PAGE sample buffer.
 Boil the sample for 5 minutes.

13. Centrifuge it at 5,000 x g for 10 seconds.

E. Western Blot Analysis

1. Load 15 μL/well of pull-down supernatant to a polyacrylamide gel (17%). It is recommended to include a pre-stained MW standard (as an indicator of a successful transfer in step 3 below).

2. Perform SDS-PAGE following the manufacturer's instructions.

3. Transfer the gel proteins to a PVDF or nitrocellulose membrane following the manufacturer's instructions.

Note: Steps 4-11 are at room temperature with agitation

4. Following electroblotting, immerse the PVDF membrane in 100% Methanol for 15 seconds, and then allow it to dry at room temperature for 5 minutes.

Note: If Nitrocellulose is used instead of PVDF, step 4 Should be skipped.

5. Block the membrane with 5% non-fat dry milk or 3% BSA in TBST for 1 he at room temperature with constant agitation.

6. Wash the blotted membrane three times with TBST, 5 minutes each time. 7. Incubate the membrane with anti-G α_{13} Mouse Monoclonal Antibody (Cat. #

21005), which has been freshly diluted 1:50~500 (depending on the amount of $G\alpha_{13}$ proteins in your sample) in 5% non-fat dry milk or 3% BSA in TBST, for 1-2 her at

room temperature with constant agitation or at 4°C overnight.

8. Wash the blotted membrane three times with TBST, 5 minutes each time. 9. Incubate the membrane with a secondary antibody (Cat. # 29002), which has been freshly diluted 1:1000 in 5% non-fat dry milk or 3% BSA in TBST, for 1 he at room temperature with constant agitation.

10. Wash the blotted membrane three times with TBST, 5 minutes each time.

11. Use the detection method of your choice such as ECL.