

Pioneering GTPase and Oncogene Product Development since 2010

## GAo PULL-DOWN ACTIVATION ASSAY KIT

## **Gα<sub>o</sub> Pull-Down Activation Assay Kit**

Cat. # 80901

## Introduction

### A. Background

A structurally diverse repertoire of ligands, from photons to large peptides, activates G protein-coupled receptors (GPCRs) to elicit their physiological functions. Ligand-bound GPCRs, in turn, function as guanine nucleotide exchange factors catalyzing the exchange of GDP bound on the G $\alpha$  subunit with GTP in the presence of G $\beta\gamma$ , causing the dissociation of the G $\alpha$  subunit from the G $\beta\gamma$  dimer to form two functional units (G $\alpha$  and G $\beta\gamma$ ). Both G $\alpha$  and G $\beta\gamma$  subunits signal to various cellular signaling pathways. Based on the sequence and functional homologies, G proteins are grouped into four families: Gs, Gi, Gq, and G12. G $\alpha$  family (including G $\alpha$ ) is the largest family of G proteins. They relay signals from many GPCRs to regulate various biological functions. There were no direct methods to measure the activation of G $\alpha$ 0 proteins by receptors (until this assay kit). Most reports used one of the downstream pathways, i.e. the inhibition of adenylyl cyclases, as a readout.

### **B.** Assay Principle

NewEast Biosciences  $G\alpha_{\circ}$ Activation Assay Kit uses configuration-specific anti- $G\alpha_{\circ}$ -GTP Mouse monoclonal antibody to measure  $G\alpha_{\circ}$ -GTP levels in cell extracts or in vitro GTP $\gamma$ S loading  $G\alpha_{\circ}$ activation assays. Anti- $G\alpha_{\circ}$ -GTP mouse monoclonal antibody is first incubated with cell lysates containing  $G\alpha_{\circ}$ -GTP. Next, the GTP-bound  $G\alpha_{\circ}$ is pulled down by protein A/G agarose. Finally, the precipitated  $G\alpha_{\circ}$ -GTP is detected through immunoblot analysis using anti- $G\alpha_{\circ}$ mouse monoclonal antibody.

### C. Kit Components

1. Anti-G $\alpha_{\circ}$ -GTP Mouse Monoclonal Antibody (Cat. # 26907): 30  $\mu$ L (1 mg/ml) in PBS, pH 7.4, containing 50% glycerol. This antibody specifically recognizes G $\alpha_{\circ}$ -GTP from



Pioneering GTPase and Oncogene Product Development since 2010

- 2. Protein A/G Agarose (Cat. # 30301): 600 µL of 50% slurry.
- 3. 5X Assay/Lysis Buffer (Cat. # 30302): 30 mL of 250 mM Tris-HCl, pH 8, 750 mM NaCl, 50 mM MgCl2, 5 mM EDTA, 5% Triton X-100.
- 4. Anti-Gα<sub>o</sub>Mouse monoclonal Antibody (Cat. # 21015): 50 μL (Img/mL) in PBS, pH 7.4, contained 50% glycerol.
- 5. 100X GTPyS (Cat. # 30303): 50 µl at 10 mM, use 5 µL of GTPyS for GTP-labeling of 0.5 mL of cell lysate.
- 6. 100X GDP (Cat. # 30304): 50 µl at 100 mM, use 5 µL of GDP for GDP-labeling of 0.5 mL of cell lysate.
- 7. HRP-Goat Anti-Rabbit IgG (Cat. # 29002): 50 µL (0.4 µg/mL) in PBS, pH 7.4, contained 50% glycerol.

## D. Materials Needed but Not Supplied


- 1. Stimulated and non-stimulated cell lysates
- 2. Protease inhibitors
- 3. 4 °C tube rocker or shaker
- 4. 0.5 M EDTA at pH 8.0
- 5. 1.0 M MgCl<sub>2</sub>
- 6. 2X reducing SDS-PAGE sample buffer
- 7. Electrophoresis and immunoblotting systems
- 8. Immunoblotting wash buffer such as TBST (10 mM Tris-HCl, pH 7.4, 0.15 M NaCl, 0.05% Tween-20)
- 9. Immunoblotting blocking buffer (TBST containing 5% Non-fat Dry Milk or 3% BSA) 10. ECL Detection Reagents

## E. Example Results

The following figure demonstrates example results seen with the  $G\alpha_{\circ}$ Activation Assay Kit. For reference only.



Pioneering GTPase and Oncogene Product Development since 2010



**Gα<sub>o</sub> Activation Assay.** Purified Gα<sub>o</sub> proteins were loaded as a control (lanes 1) or immunoprecipitated after treated with GDP (lane 2) or GTPγS (lane 3). Immunoprecipitation was done with the anti-Gα<sub>o</sub>-GTP monoclonal antibody (Cat. # 26907). Immunoblot was with an anti-Gα<sub>o</sub> polyclonal antibody (Cat. # 21015).

## **Assay Procedure**

## A. Reagent Preparation

**1X Assay/Lysis Buffer:** Mix the 5X Stock (Cat. # 30302) briefly and dilute with deionized water to make 1X buffer. Just prior to usage, add protease inhibitors such as 1 mM PMSF, 10 µg/mL leupeptin, and 10 µg/mL aprotinin.

## **B. Sample Preparation**

#### **Adherent Cells**

- 1. Culture cells (one 10-cm plate, ~10<sup>7</sup> cells) to approximately 80-90% confluence. Stimulate the cells with activator or inhibitor as desired.
- 2. Aspirate the culture media and wash twice with ice-cold PBS.
- 3. Completely remove the final PBS wash and add ice-cold 1X Assay/Lysis Buffer (See Reagent Preparation) to the cells (0.5-1 mL per 10 cm tissue culture plate).
- 4. Place the culture plates on ice for 10-20 minutes.
- 5. Detach the cells from the plates by scraping with a cell scraper.
- 6. Transfer the lysates to appropriate size tubes and place on ice.
- 7. If nuclear lysis occurs, the cell lysates may become viscous and difficult to pipette. If this occurs, lysates can be passed through a 27½-gauge syringe needle
- 3-4 times to shear the genomic DNA.



Pioneering GTPase and Oncogene Product Development since 2010

- 8. Clear the lysates by centrifuging at 12,000 x g and 4°C for 10 minutes.
- 9. Collect the supernatant and store the sample (~1-2 mg of total protein) on ice for immediate use, or snap freeze and store at -70°C for future use.

#### **Adherent Cells**

- 1. Culture cells and stimulate with activator or inhibitor as desired.
- 2. Perform a cell count and then pellet the cells through centrifugation.
- 3. Aspirate the culture media and wash twice with ice-cold PBS.
- 4. Completely remove the final PBS wash and add ice-cold 1X Assay/Lysis Buffer (See Reagent Preparation) to the cell pellet (0.5-1 mL per 10<sup>7</sup> cells).
- 5. Lyse the cells by repeated pipetting.
- 6. Transfer the lysates to appropriate size tubes and place them on ice.
- 7. If nuclear lysis occurs, the cell lysates may become viscous and difficult to pipette. If this occurs, lysates can be passed through a 27½-gauge syringe needle 3-4 times to shear the genomic DNA.
- 8. Clear the lysates by centrifuging at 12,000 x g and 4°C for 10 minutes.
- 9. Collect the supernatant and store sample on ice for immediate use, or snap freeze and store at -70°C for future use.

## C. In vitro GTPyS/GDP Protein for Positive and Negative controls

Note: In vivo stimulation of cells will activate approximately 10% of the available Ar13, whereas in vitro GTPyS protein loading will activate nearly 90% of Ar13.

- 1. Aliquot 0.5 mL of cell extract (or 1 µg of purified Ar13 protein) into two microcentrifuge tubes.
- 2. To each tube, add 20 µL of 0.5 M EDTA (final concentration of 20 mM).
- 3. Add 5  $\mu L$  of 100 X GTP $\gamma$ S (Cat. # 30303) to the first tube as a positive control.
- 4. Add 5 µL of 100 X GDP (Cat. # 30304) to the second tube as a negative control.
- 5. Incubate both tubes at 30°C for 30 minutes with agitation.
- 6. Stop loading by placing the tubes on ice and adding 32.5  $\mu$ L of 1 M MgCl<sub>2</sub> (final concentration of 60 mM).

## D. Affinity Precipitation of Activated G Protein

- 1. Aliquot 0.5-1 mL of cell lysates (about 1 mg of total cellular protein) to a microcentrifuge tube.
- 2. Adjust the volume to 1 mL with 1X Assay/Lysis Buffer (See Reagent Preparation).
- 3. Add 1 µL anti-Ar13-GTP antibody (Cat. # 26907).
- 4. Prepare the protein A/G Agarose bead slurry (Cat. # 30301) by resuspending through vertexing or titrating.
- 5. Quickly add 20 µL of resuspended bead slurry to above tube.
- 6. Incubate the tube at 4°C for I hour with gentle agitation.



Pioneering GTPase and Oncogene Product Development since 2010

- 7. Pellet the beads through centrifugation at 5,000 x g for 1 min.
- 8. Aspirate and discard the supernatant (making sure not to disturb or remove the bead pellet).
- 9. Wash the beads 3 times with 0.5 mL of 1X Assay/Lysis Buffer, centrifuging and aspirating each time.
- 10. After the third wash, pellet the beads through centrifugation and carefully remove all the supernatant.
- 11. Resuspend the bead pellet in 20 µL of 2X reducing SDS- PAGE sample buffer.
- 12. Boil the sample for 5 minutes.
- 13. Centrifuge it at 5,000 x g for 10 seconds.

## E. Western Blot Analysis

- 1. Load 15 µL/well of pull-down supernatant to a polyacrylamide gel (17%). It is recommended to include a pre-stained MW standard (as an indicator of a successful transfer in step 3 below).
- 2. Perform SDS-PAGE following the manufacturer's instructions.
- 3. Transfer the gel proteins to a PVDF or nitrocellulose membrane following the manufacturer's instructions.

Note: Steps 4-11 are at room temperature with agitation

- 4. Following electroblotting, immerse the PVDF membrane in 100% Methanol for 15 seconds, and then allow it to dry at room temperature for 5 minutes.
- Note: If Nitrocellulose is used instead of PVDF, step 4 Should be skipped.
- 5. Block the membrane with 5% non-fat dry milk or 3% BSA in TBST for 1 he at room temperature with constant agitation.
- 6. Wash the blotted membrane three times with TBST, 5 minutes each time.
- 7. Incubate the membrane with anti-Arl3 Mouse Monoclonal Antibody (Cat. # 21015), which has been freshly diluted 1:50~500 (depending on the amount of Arl3 proteins in your sample) in 5% non-fat dry milk or 3% BSA in TBST, for 1-2 her at room temperature with constant agitation or at 4°C overnight.
- 8. Wash the blotted membrane three times with TBST, 5 minutes each time.
- 9. Incubate the membrane with a secondary antibody (Cat. # 29002), which has been freshly diluted 1:1000 in 5% non-fat dry milk or 3% BSA in TBST, for 1 he at room temperature with constant agitation.
- 10. Wash the blotted membrane three times with TBST, 5 minutes each time.
- 11. Use the detection method of your choice such as ECL.